Installing Anaconda on Ubuntu/Linux

- 1. Download the Anaconda .sh file. You may do it in two ways:
 - a. Manually download from this link.
 - b. On your terminal, type the following:

wget https://repo.anaconda.com/archive/Anaconda3-2021.11-Linux-x86 64.sh

This should download the Anaconda3 file to your working directory.

2. On your terminal, verify the integrity of your downloaded file:

sha256sum Anaconda3-2021.11-Linux-x86 64.sh

The list of Anaconda file hashes can be found <u>here.</u> If the hashes don't match, please redownload. That file may be corrupted.

3. Run the Anaconda script: bash Anaconda3-2021.11-Linux-x86 64.sh

During the installation process, it may prompt the following questions:

- Do you accept the license terms? yes
- Anaconda will be installed in this location:
 - You may choose to change the location by typing in new directory
 - Click enter if you're okay with the default location
- Do you wish the installer to initialize Anaconda3? yes
- 4. If you accidentally skipped the last question in <step 3> and conda command becomes unavailable:
 - You can opt to reinstall; or
 - On your terminal: export PATH=/path/to/anaconda3/bin:\$PATH
 - Or to set the path permanently, open your shell script (usually ~/.bashrc) and type in the export PATH line there.
- 5. Activate installation: source ~/.bashrc

Common conda commands

Below are a list of common conda commands:

- Creating an environment: conda create -n <env_name> python=3
 - You may specify the python version through the python argument
- Activating an environment: conda activate <env name>
- Deactivating/exiting your environment: conda deactivate
- List all conda environments: conda env list
- Deleting an environment: conda remove -n <env name> --all
- Deleting a package: conda remove -n <env_name> <pkg_name>

More about conda (including cheat sheet) can be found here.